The Whole architecture of the code.

Root to CSV

文件: Root2CSV.py 类: Root2CSV

主要函数是: run()

Check()

oRoot2CSV=Root2CSV(homeRoot=iParser.homeRoot,homeCSV=iParser.homeCSV,channels=iParser.channels,numEventPerFile=iParser.numEventPerFile,numProcess=iParser.numProcess)

oRoot2CSV.Run()

oRoot2CSV.Check()

API:

Class Channel(homeCSV,channels=None):

Parameters:

homeCSV: home of csv folder

channels=None: channels used. If None, all channles are used.

Purpose

根据csv文件夹中的子文件夹,给出channels.如果在输入的时候给定了channels,那么,直接使用这些channels. According to the subfolders in the csv folder, channels are given by the names of the subfolders. If the chann are given at the time of input, these channels are used directly.

File

Channel.py.

Functions

GetChannels()

return channels

GetChannels()

return channels

Get channels list from folder or from input

Example

```
homeCSV='/home/i/IGSI/data/csv'
# channels=['T09_T05_55_D0', 'T09_T06_55_Dch', 'T09_T07_55_Ds', 'T09_T08_55_Lam', 'T09_T09_55_Lamc']
channels=None
oChannel=Channel(homeCSV=homeCSV,channels=channels)
oChannel.GetChannel()
```

Class

Root2CSV(homeRoot,homeCSV,channels=None,numEventPerFile = 2048,numProcess=10):

Parameters:

homeRoot

homeCSV: home of csv folder

channels=None

numEventPerFile=2048: number of events in one csv file

numProcess=10: numbers of processor to used

Purpose

将root文件转变成csv文件,并储存在homeCSV文件夹中. Convert root files to csv files and store them in the homeCSV folder.

File

Root2CSV.py

Functions

ChangeChannelName()

No return.

Rename the channels from "T00_DPM_24" to "T00_24_DPM" with format "Method_Energy_Data"

LogGetNumEventMC(root)

return numEventMC

Return the number of events according to the log based on the name of root file.

RootGetTree(root)

Return trees name from a root file.

RootGetBranch(self,root,tree):

Return branches from the specific root and tree.

RootGetData(self,root,tree,branches)

Return data from specific root, tree and branches

RootRead_Process_Write_Channel(self,channel)

No return. This function reads the root files from one channel and convert to csv files and write down the csv files on disk.

It creates a runLog file in every channel in the csv folders.

In the runLog file, there are:

nnumEventMC_PID

numEventMC

numEventMC_PID/numEventMC And also: 'id'

'branch'

'mean'

'std'

'min'

'max'

'std=0'

if 'std=0' is True, this std of this branch is 0.

RootRead_Process_Write_Channels(self)

No return.

Do RootRead_Process_Write_Channel(channel) in parallel.

Run()

No return.

Run function RootRead_Process_Write_Channels(self).

Check()

Return channelsChecked, channelsNotChecked

channels Checked: channel list in which channels are convert successfully. channels NotChecked: channel list in which channels are conver failed.

Check every channel if all root files are convert to csv from root and store on disk. a log file checkLog is created in homeCSV main folder.

DelFolderChannelsNotChecked()

No return.

Delete all the channels which are in the list channelsNotChecked.

SetChannel(channels):

No return.

Set channels online.

ReRun():

No return.

Run DelFolderChannelsNotChecked() to delete all the channels which are in the list channelsNotChecked. Set channels online with list channelsNotChecked.

Run and Check.

Example

Class Branch(homeCSV,channels=None,pidUse=True):

Parameters:

homeCSV channels=None pidUse=True

Purpose

Select branches

File

Branch.py

Functions

BranchSel(branchAllList)

Return branchSel,branchSelNO,branchAllListRemain branchSel: + branchSelNO: - branchAllListRemain: unknown

Normally, the branchAllList is gotten from columns of csv files.

Example

```
homeCSV='/home/i/iWork/data/csv'
channels=None
pidUse=True

oBranch=Branch(homeCSV,channels,pidUse)

branchAllList=pd.read_csv('/home/i/iWork/data/csv/T00_DPM_24/0000000_0002048.csv',nrows=0).columns.tol
ist()
print(branchAllList)
branchSel,branchSelNO,branchAllListRemain=oBranch.BranchSel(branchAllList)
print(branchSelNO)
print(branchSelNO)
print(branchAllListRemain)
```

Class

Data(homeCSV,channels=None,ratioSetTrain=0.7,ratioSetTest=0.3,ratioSetValid=0.):

Parameters:

homeCSV channels=None ratioSetTrain=0.7 ratioSetTest=0.3

r	ล	ti	O	S	6	t١	V	a	li	d	=	0	i.
	ч	u	v	$\overline{}$	_	·	v	ч	"	u		v	

Purpose

This Class is mainly used in DateSet...

Split csvList to listCSV4Test ,listCSV4Valid and listCSV4Train

'listCSV4Test' 'listCSV4Valid' 'listCSV4Train'

'labels' 'labels' 'numClasses' 'branch4Train'

File

Data.py

Functions

GetListCSV4Test():

return self.listCSV4Test

GetListCSV4Valid():

return self.listCSV4Valid

GetListCSV4Train():

return self.listCSV4Train

GetLabels():

return self.labels

GetNumClasses():

return self.numClasses

GetBranch4Train():

return self.branch4Train

branchTrainLog()

No return.

Write log branchTrainLog.

Content:

branchAll: 401

beame beamm beamp beamphi ...

branch4Train (Train !!!): 232 beamp esapl escir esfw1 ...

branch4TrainNOUSE: 169

beame beamm beamphi beampt ...

branchWhilelist NOT exist...: 7

d d0 ddd ...

branchBlacklist NOT exist...: 0

_Branch4Train()

No return.

Read log branchLog to get branchAll and branchAll.

branchWhitelistHand and branchBlacklistHand are read here.

branchWhitelistHand is read first, and branchBlacklistHand read later, which means that the priority of branchBlacklistHand is higher than it of branchWhitelistHand.

__Labels()

No Return.

Arrange all the channels with labels. DPM:0

sig: +=1

_Labels()

No Return.

Set chanels with labels...

Label(iChannel)

return label

Return a label given the iChannel.

```
_Data()

No Return.
Get the ratioEvent of all Channels.

_DataSplit()

No Return.
Split csv list to lists of Test, Valid and Train.

__GetList_While_Black(iListFile)

No return.
Read branchWhitelistHand and branchBlacklistHand to get list.
```

Example

```
homeCSV='/home/i/iWork/data/csv'

oData=Data(homeCSV,channels=None,ratioSetTrain=0.7,ratioSetTest=0.3,ratioSetValid=0.)

print('listCSV4Test')
print(oData.GetListCSV4Test())
print('listCSV4Valid')
print(oData.GetListCSV4Valid())
print('listCSV4Train')
print(oData.GetListCSV4Train())

print('labels')
print(oData.GetLabels())

print('numClasses')
print(oData.GetNumClasses())

print('branch4Train')
print(oData.GetBranch4Train())
```

Class

DataSet(homeCSV,channels,setTrain=1,setTest=0,setValid=0,ratio SetTrain=0.7,ratioSetTest=0.3,ratioSetValid=0.,readMethod=0):

Parameters:

homeCSV channels setTrain=1 setTest=0 setValid=0 ratioSetTrain=0.7 ratioSetTest=0.3 ratioSetValid=0. readMethod=0

Purpose

DataSet for NN.

File

DataSet.py

Functions

Label2Data()

No Return
label2CSV
Writedown a log named label2CSVLog

__len__()
return number of iterm

__getitem__()

ReadCSV()

No Return. read in data and label from csv parallelly Create one processor based on every class. Call function ReadCSV_OneFile(iClass)

ReadCSV_OneFile(iClass)

return data=(iData,iLabel)

return (iData,iLabel) for iClass.

- 1. Given iClass as label: → iLabel
- 2. Get csv list accoring to iClass

4. read in one csv :-> iData5. return (iData,iLabel)
Example
Class Channel(homeRoot,channels=None):
Parameters:
Purpose
File
Functions
GetChannels()
Example
Class Channel(homeRoot,channels=None):
Parameters:
Purpose
File
Functions
GetChannels()
Example

3. Choose one csv randomly form csv list

weekly_20200421.md to weekly_	_20200421.pdf by MARKDOWN-THE	MEABLE-PDF